

1. Driver Installation

The Doc is for the PCI driver installation only.

As of Feb 15, 2011 there are now all new drivers for the PCI PC Watchdog that support 32 and 64 bit versions. The old drivers are still on the CD if you need to use them. They can be found in a .ZIP file:

Drivers\PN1130_PCI_Win32-64__Archive\Old_PCI_Win32.zip

The new drivers now have a preferred method of install as well as an older XP style. See the next two sections.

1.1 Preferred Driver Installation Method


When you power up the PC you *may* get a found new hardware screen (depends on Windows version). Ignore this screen and just click the cancel button. Put the CD in the drive and navigate to the following directory depending on your version of windows:

32 Bit Versions: Drivers\PN1130_PCI_Win32-64\i386

64 Bit Versions: Drivers\PN1130_PCI_Win32-64\amd64

Run the program dpinst.exe. It will install the driver and it will put an entry in the Ad_Remove Programs in Control Panel to allow removal of the driver.

If the driver installs OK you should see a final window like this one:



You may be required to restart the computer before the changes go into effect.

1.2 XP Style Installation (Not Recommended)

When you power up the PC you *may* get a found new hardware screen (depends on Windows version) such as this one from Windows XP:



Make sure the CD is in the PC drive and click next to allow Windows to find the driver files.

If you get a window like this – make sure you select the proper driver for your version of Windows, 32 or 64 bit.

